

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
<b>Version 6.00</b>						
General	Added the EZ Form Design Wizard.	M	X	X		6.00
General	Added new Change Form Color option to the Format menu to allow the user to change the form color of all the fields on the form at the same time.	M	X	X		6.00
Response	Changed the Default Response Ink from Gray 55% to Gray 50%.	M	X	X		6.00
Response	Program now checks for Non Bubble Characters in the replacement characters.	M	X	X		6.00
Response	Bubble Density error messages were modified to be more accurate.	M	X	X		6.00
Text	Removed bogus fonts from font lists that start with the @ symbol.	M	X	X		6.00
Image Region	Image Region field changes would not be saved if the changes were made before the field was put on the workspace. The Browse button would cause the software to end abnormally.	B		X		6.00
Graphic	The program was modified so a pasted bitmap could be properly added to the form.	B	X	X		6.00
Printing	Modified the entry boxes for beginning and ending Lithocodes to look different to avoid confusion.	M	X	X		6.00
General	Repaired a problem when opening forms with empty back pages.	B	X	X		6.00
Response	Some bubble fonts were removed. The program will automatically select the new correct font when old forms are opened.	M	X			6.00
Paste	The message "Do you want to paste into the selected field?" was shown when a Response object is selected. Since a new Response object is always created, the question should not have been shown in the first place.	B	X	X		6.00
Paste	Added the field type to the error message warning about pasting into a selected field to make it more accurate.	M	X	X		6.00
Colors	Removed unneeded Gray Scales and generally cleaned the color list.	M	X	X		6.00

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
General	Modified "Load Character Map" to "Font Viewer" on the View menu to be more descriptive.	M	X	X		6.00
General	Added form backups to the program in case of problems with the form files.	M	X	X		6.00
Scanning	Modified the program so the scan template will be automatically created when you click on Launch the Template Editor if it does not exist.	M	X	X		6.00
Scanning	Modified the program so the scan template will be automatically created when you click on "Scan Forms" if it does not exist.	M	X	X		6.00
Scanning	Modified the program to issue an error if you click on "Scan Forms" before you have created the scan template.	M	X	X		6.00
Scanning	Changed the identification information to row and column number for the SetupOrderofOutputFields feature on the Scanning menu.	M	X	X		6.00
Scanning	On the Scan Properties dialog box, the Values column no longer appears when the field is Numeric.	B	X	X		6.00
Colors	Changed all default colors to Black/Gray and added an Warning for Response colors over 60%.	M	X	X		6.00
General	Removed all 6 rows or columns to the inch.	B		X		6.00
Data Merge	Repaired problem where if a comma or tab field was too long, it would continue to fill out grid that did not exist.	B	X	X	X	6.00
Response	Program now gives an error if the user does not fill in the Bubble and Barcode field names on the Properties dialog box.	M	X	X		6.00
General	Strengthened warnings about changing bubble density.	M	X	X		6.00
General	Removed the .bkt file extension - all forms, single page or multi-page, use the .fsl extension.	M	X	X		6.00
General	Added Double sided margin set.	M	X	X		6.00
Data Merge	In Data Merge, for Multiple Characters, automatically puts the current labels in the entries which can then be modified.	B	X	X	X	6.00

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Scanning	Modified Scan Field Properties to Link properties button and added Data Merge tab for a linked Response object.	M	X	X		6.00
General	Added "Upgrade Version" to all menus.	M	X	X		6.00
Data Merge	The "Number of Copies Field" warning message would come up erroneously.	M	X	X	X	6.00
General	Added checks for illegal characters in Field Names.	B	X			6.00
<b>Version 5.08</b>						
Error Messages	Certain error messages were being shown on the screen when using the CLI.	B	X	X		5.08
Linking	Repaired a problem where the software would exit abnormally if certain field types were linked.	B	X	X		5.08
Lines	Corner type was showing up incorrectly on the Object Bar for Lines.	B	X	X		5.08
Linking	Modified the way linking takes place for List type fields. The software now uses the orientation of the scan field to determine whether numbering is left to right or top to bottom.	M	X	X		5.08
Form Files	Adding extra checking when saving form files to network drives to stop some save errors.	M	X	X		5.08
Tools	Changed the Tools menu item "Renumber Reponses" to "Renumber Text or Reponses".	M	X	X		5.08
Graphs	Repaired a problem where the graphic would disappear from the screen.	B	X	X		5.08
Operating System	Modified the software to accommodate changes in Microsoft Windows Vista.	M	X	X		5.08
Setup	Removed "Change Colorset" command.	M	X	X		5.08
Paper Size	Made some modifications to allow better usage of 11 x 17 paper.	M	X	X		5.08

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Timing Track	Repaired incorrect Timing Mark placements (Right, Bottom) when form is not 6x6 or 48 columns.	M	X			5.08
<b>Version 5.07</b>						
Data Merge	Add the ability to preplug a bubble where there is more than 1 character to match in the data field.	M	X	X	X	5.07
Data Merge	For Data Merge, made case (upper or lower) of text moot.	M	X	X	X	5.07
Data Merge	In Data Merge, corrected the Data Length calculation in certain circumstances.	B	X	X	X	5.07
Responses	Repaired a problem where the proper Row and Column Gap was not being calculated when creating a new Response field.	B	X	X		5.07
Barcodes	Repaired a problem where Magenta would exit if you selected an unlinked barcode, then, clicked on the Scanning tab.	B		X		5.07
Lines	Corner type was showing up incorrectly on the Object Bar for Lines.	B	X	X		5.07
Printing	Print Multiple was active in cases where it should not have been.	B	X	X		5.07
Printing	If Magenta OMR version and no Timing Track was present, the setting of margins was not working properly.	B	X			5.07
<b>Version 5.06</b>						
Scanning	Repaired problem where the Scan properties were not being correctly set up for other fields in a link.	B	X	X		5.06
General	Repaired a problem so the controls would get set correctly for Landscape forms when changing to Landscape.	B	X	X		5.06
Alignment	Changed Move Print Image with booklet open, to not ask about changing all pages if only one page open.	M	X			5.06
General	Reduced the number of Timing Marks to 83 for 8 per inch. Makes for easier form alignment.	M	X			5.06

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Alignment	Changed Alignment procedure.	M	X			5.06
<b>Version 5.05</b>						
Responses	Added "Select All Response Objects" to Edit menu.	M	X	X		5.05
Booklets	Added ability to open a form and booklet.	M	X	X		5.05
Scanning	On the Scanning Tab of the Field Properties dialog box, made Respondent ID and Grade always active.	M	X	X		5.05
Booklets	Repaired File/SaveAs rename problem	B	X	X		5.05
Booklets	An erroneous error message about what kind of form (Magenta or Magenta for Office) was being opened was appearing.	B	X	X		5.05
General	If no values in HKEY_LOCAL_MACHINE registry section, Magenta would not start up.	B	X	X		5.05
Booklets	Repaired all problems in file saving routines.	B	X	X		5.05
Scanning	Repaired a problem where a "...Not enough fields..." error message was appearing incorrectly for Scan Field Types ALLTHATAPPLY and BOOLEAN	B	X	X		5.05
Scanning	Repaired a problem where the Scan Field Type was not being set for certain link types.	B	X	X		5.05
Scanning	Repaired a problem the Boolean field was not being set up correctly in the scan template.	B		X		5.05
Predefined Fields	Predefined fields - made the 0-9 and A-Z grids more flexible.	M	X	X		5.05
Shading	Modified the "...do not use shade colors greater than 10%.." error message to only come up when a Shade object is touching a Response object and to 10% from 5% and to only come up once when changing the color of multiple Shade objects.	M	X	X		5.05
Booklets	Add the ability to save an .fsl as a .bkt to convert a form to a booklet.	M	X	X		5.05

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Scanning	Repaired a problem where Shade, Lines and Boxes were being incorrectly checked for fields between bubbles.	B		X		5.05
Scanning	Repaired a problem where the Respondent ID variable was not getting set in the scan template.	B	X	X		5.05
Scanning	Repaired a problem where some fields were not getting their Scan parameters set correctly before they were saved to the form file.	B	X	X		5.05
Booklets	When opening a Version 5 booklet, some files caused an erroneous conversion message.	B	X	X		5.05
Responses	On the Field Properties dialog box, General tab, removed some erroneous errors for 0 entries in the Number of Rows or Columns.	B	X	X		5.05
Add Colors	Repaired some problems when adding colors.	B	X	X		5.05
Scanning	Added "Unnamed Fieldn" auto-naming fields so the user can use those names to more easily identify unnamed fields.	M	X	X		5.05
Scanning	Added Row and Column to more easily identify some fields.	M	X	X		5.05
Scanning	Added Textual or Numeric to the Scan Properties dialog box.	M	X	X		5.05
Booklets	If the pages of a booklet get converted before opening the booklet, Magenta now opens the booklet correctly anyway.	M	X	X		5.05
Responses	Removed Bold and Italic buttons from Response Object Bar and Properties dialog box.	M	X	X		5.05
<b>Version 5.04</b>						
Response Bubbles	Add 1-10 and 1-12 to Response Values list.	M	X	X		5.04
File Saving	FileSaveAs did not work if you saved form into another folder.	B	X	X		5.04
File Saving	When doing a FileSaveAs with a fsl/bkt file, any .bmp files specified in the .fsl would not be saved in the new .fsl/bkt file.	B	X	X		5.04

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Scanning	Set up Boolean fields as Multi-question.	B	X	X		5.04
Scanning	Repaired a problem where the rows or columns for Boolean fields were not be set correctly.	B	X	X		5.04
Colors	Modified "NO FONT or INK" error message.	M	X	X		5.04
Colors	Changed the word "Ink" to "Color" throughout the program.	M	X	X		5.04
Scanning	On Scan Field Properties dialog box, adding blank rows for Questions was not working properly.	B	X	X		5.04
Scanning	When creating the scan template (.omr) and a field is to be graded, blanks should return "Nothing" not "blank".	M		X		5.04
Scanning	Repaired a problem concerning single bubble fields and combining.	B	X	X		5.04
Renumber Responses	Modified Renumber Responses so it would sort by position only on form.	B	X	X		5.04
<b>Version 5.03</b>						
Printing	Repaired Merge Data printing issue with booklets.	B	X	X	X	5.03
Aligning Text	Repaired a problem where Magenta exited if you attempted to "Align Text to Responses" with no text fields selected.	B	X	X		5.03
<b>Version 5.02</b>						
Printing	Added the ability to print a single page.	M	X	X		5.02
Printing	When printing a duplex booklet, an error message about printing in duplex was showing up incorrectly .	B	X	X		5.02
<b>Version 5.01</b>						

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Scanning	Changed the .rco file to set the "Use Default Names" parameter to ON (Field Properties - Advanced tab).	M	X			5.01
Booklets	If you had multiple pages in a booklet and were printing without Duplex on, you got a warning message for every page (making PDF).	B	X	X		5.01
<b>Version 5.0</b>						
Autosave	An Autosave feature was added.	M	X	X		5.0
Barcodes	Modified the way a Text Object is set to be a Barcode field. Instead of checking the box labeled "When scanning, this is a Barcode Field:" on the General tab of the Field Properties Dialog Box, you now set the Scan Field Type to BARCODE on the Scanning tab of the Field Properties Dialog Box.	M	X	X		5.0
Barcodes	The scan field type will be set to BARCODE if the word "barcode" is in the font name.	M	X	X		5.0
Barcodes	Added error message to prevent turning a Text Object into a Text Box if the field is set to barcode.	B	X	X		5.0
Booklets	Modified the way forms and booklets work - there will now be only one file (.bkt or .fsl) that will contain the .bkt, .fsl and .bmp files.	M	X	X		5.0
Booklets	When you create a new booklet, Magenta now opens the first page instead of the Booklet Dialog Box.	M	X	X		5.0
Booklets	Added the options "File/New/Front Page" and "File/New/Back Page" to the File Menu, to add forms to a booklet.	M	X	X		5.0
Booklets	Added "Insert Form" option to the Booklet Dialog Box to allow users to add forms created as separate forms into a booklet.	M	X	X		5.0
Booklets	Added "Copy Form" option to the Booklet Dialog Box to allow users to save a form to an .fsl file outside a booklet.	M	X	X		5.0
Booklets	When saving a booklet, the question asking if you wanted to close the booklet was being asked twice.	B	X	X		5.0
Copying	When copying a Text object the Text will be set back to the default "abc".	M	X	X		5.0
Edit Inks	New colors - Brown, Peach - were added.	M	X	X		5.0

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Error Messages	Added the error message "All forms in a booklet must have the same orientation (Portrait or Landscape)" if you try to create a form with a different orientation.	B	X	X		5.0
Error Messages	When loading a file with links, erroneous missing Timing Marks messages were removed.	B	X			5.0
Error Messages	Modified shade error message to read 5% for Magenta Office forms.	B		X		5.0
Error Messages	When using SquareNormal, etc. fonts, an incorrect error message that the form was created using standard version was given.	B		X		5.0
Field Labels	When adding a field, if the field label was changed before it was placed on the workspace, the changes are lost when the field is drawn on the work space.	B	X	X		5.0
Field Labels	When loading a barcode field, the field label would be lost.	B	X	X		5.0
Field Labels	Right click did not work for fields with the same field label. Also, added extra information to the descriptions of fields.	M	X	X		5.0
Images	Hyphens and underscores are now allowed in Graphic file names (.bmp).	M	X	X		5.0
Installation	Form files (*.fsl) and image files (*.bmp) are now moved to the new folders.	M	X	X		5.0
Installation	In the form files (*.fsl), references to the Images folder for graphics are now updated to reflect the new Images folder.	M	X	X		5.0
Merge Data	When using Segments and Comma delimited files, a number of problems were repaired.	B			X	5.0
Move Print Image	Added instructions to the Move Print Image Dialog Box.	M	X	X		5.0
Move Print Image	When changing Snap to Grid values, they are applied to all open forms, not just the active one.	M	X	X		5.0
Move Print Image	When performing a Move Print Image on a booklet, you are now asked if you want to make the same change on all like pages.	M	X	X		5.0
Paste Special	Generally, if you put local Magenta fields in the Paste buffer, copies will be made when you paste.	M	X	X		5.0

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Paste Special	If you copy text from outside Magenta, it will be copied into a new TextBox. If a Textbox is already selected it will be copied into that one.	M	X	X		5.0
Paste Special	Characters from bubble fonts can be pasted into a selected Response Object.	M	X	X		5.0
Paste Special	Paste Special now allows text such as for questions and labels to be pasted into separate Text Objects.	M	X	X		5.0
Properties Dialog Box	On the Field Properties Dialog Box for a Response Object, General tab, the Number of Rows/Cols get properly grayed when not valid.	B	X	X		5.0
Responses	The "Stay Away" gray area around bubbles only went around each bubble instead of covering all the area in between.	B		X		5.0
Responses	Uneven spacing in Replacement is now allowed. Creating the scan template works with this. Uneven spacing is never a Grid.	M	X	X		5.0
Responses	In Magenta Office only, when Snap to Grid is turned off, the user can pixel move Response Objects.	M		X		5.0
Linking	The Scan Properties dialog box comes up automatically when you link fields together that have at least one Response object.	M	X	X		5.0
Linking	Double clicking on any part of a link will cause the Scan Properties Dialog Box to appear for that link.	M	X	X		5.0
Linking	When linking, if you have bubbles with greater than 1 digit inside the bubble (10, 11, etc.), the numbers did not get put in the Values area correctly.	B	X	X		5.0
Linking	Linking with no field labels included can cause a General Protection Fault.	B	X	X		5.0
Scanning	Modified the Scan Properties Dialog Box to be more complete by adding new properties and allowing text to be moved around when it is not in the proper category (Question, Label, Other).	M	X	X		5.0
Scanning	On the Reorder Scan Fields Dialog Box, the question text was added to the field to distinguish fields that were given the same field label.	M	X	X		5.0
Scanning	Added ability to create scan template file (.omr).	M		X		5.0
Scanning	Added "Setup Order of Output Fields" and "Create Scan Template" to the Scanning submenu.	M		X		5.0

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Scanning	Change "Reorder Scan Fields" to "Setup Order of Output Fields".	M	X			
Scanning	On the "Setup Order of Output Fields" dialog box, the question text was added to the field to distinguish fields that were named the same thing.	M		X		5.0
Scanning	Added the Scanning tab to the Field Properties Dialog Box.	M		X		5.0
Scanning	Added the Tools/Image Clip option (also to the Toolbar) to allow the addition of an Image Clip/Input field to Remark Office Scan Template	M		X		5.0
Scanning	Added an alignment procedure to align the scan template.	M		X		5.0
Scanning	Added the Scan Properties Dialog Box.	M		X		5.0
Scanning	A 100 scan field limit when using Reorder Scan Fields was eliminated.	B	X			5.0
Scanning	When "Setting up Order of Output Fields" and some fields were moved, if a field was selected on the workspace the program might cause a General Protection Fault when OK was clicked.	B	X			5.0
Scanning	If the Scan tab on the Properties Dialog Box has been activated for a field, the choices and labels were not being recalculated correctly when changes were made.	B	X			5.0
Scanning	On the Reorder Scan Fields Dialog Box, when you move one member of a link, the others will be automatically moved.	M	X			5.0
Scanning	Modified scan template to set Form ID same on back as on front unless actually different.	M	X			5.0
Saving Form	When you try to save a form that has objects that have been placed off the workspace, an error will be issued and the objects will be put back on the workspace.	M	X	X		5.0
Shading	Changed TextBox Background ink from Gray 3% to Gray 8%.	M	X	X		5.0
Shading	The "Stay Away" gray area around bubbles has been changed to cross hatch to help distinguish it from regular shade.	M		X		5.0
Text	"Replacement Characters" has been replaced with "Response Values or Text".	M	X	X		5.0

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Text	Text now centers properly on grid when Snap to Grid is ON.	M	X	X		5.0
Text	Text from one Text Object can now be copied and pasted into anotherTselected Text Object using Ctrl-C and Ctrl-V.	M	X	X		5.0
Text	Removed changing of text alignment when using alignment tools. This previous modification had unintended consequences.	M	X	X		5.0
Text	You could not change the font of a Text Object before putting the Text Object on the workspace.	B	X	X		5.0
Text Boxes	When loading a form, single line Text Boxes could be several lines tall.	B	X	X		5.0
Paper Size	A new paper size was added: Other. This paper size allows you to enter any size paper.	M	X	X		5.0
Paper Size	Paper Sizes were added when printing so they would be correct in .PDF files.	B	X	X		5.0
Windows	Removed "New Window" from the Windows submenu.	M	X	X		5.0
<b>Version 4.11</b>						
Defaults	Changed Default Background ink to default to the last chosen and other changes	M	X	X		4.11
Error Messages	When opening a form, the main window was not drawing if an Error Message Box was displayed.	B	X	X		4.11
Lines	For Windows 95/98/me Line types were showing up as all solid – dotted or dashed lines larger than width of 1 cannot show on the screen but do print correctly.	B	X	X		4.11
Merge Data	The printing function no longer exits if given a wrong record # (EX: Record # too high).	B			X	4.11
Merge Data	When printing, added ability to specify ending record # (A = All).	M			X	4.11
Merge Data	Merge Data was not printing "Print & Slug" text inside the boxes created by "Box Responses".	B		X		4.11

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Merge Data	Changed all Error Messages from "Data Merge" to "Merge Data" for consistency.	M	X	X		4.11
Move Print Image	The margins were not being saved correctly.	B		X		4.11
Properties Dialog Box	Removed extra word "when" on Welcome Dialog Box.	B		X		4.11
Responses	The pull-down list of Response Object standard character choices was added to with things like "5 Blank Bubbles" and "5 Blank Bubbles with Spaces".	M	X	X		4.11
Samples	Added more sample files.	M		X		4.11
Shading	Modified shading to be 5% in sample form files.	M		X		4.11
ToolBar	Added TOOLTIPS to Print and Spell Checker Tools.	M	X	X		4.11
<b>Version 4.10</b>						
Barcodes	In the font list, bar code fonts now print as their name instead of using the characters in the font itself.	M	X	X		4.10
Box Responses	For Magenta Office – Added a Box Responses feature. This is already in Magenta	M		X		4.10
Error Messages	The warning message that tells the user that one Response Object overlaps another will only be given when creating Scan Template. Overlapping of Objects is allowed and can be desirable.	M	X			4.10
Error Messages	The warning message that tells the user that a Form File (.FSL) was created by the Office version for the standard version of Magenta and vice-versa will only be shown one time for a booklet instead of for each form in the booklet.	M	X	X		4.10
Fonts	After creating a new form and putting a Timing Track on the form, if the user then started to place a Response Object on the form and changed the FONT, the font would revert back to ALSCAN.	B	X			4.10
Fonts	On Timing, Skunk and Response Objects, Magenta was not displaying the correct default font for the bubble configuration.	B	X	X		4.10
Form ID	Changed "Skunk Marks" to "Form ID" on Main Menu.	M	X	X		4.10

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Images	A warning message was added to stop the user from using image filenames with hyphens in them. This causes a problem when the form is reopened.	M	X	X		4.10
Images	Set the default Graphic directory on the Browse Dialog Box to the directory of the file and put the filename for an already existing graphic in the edit box.	M	X	X		4.10
Merge Data	On a Merge Data field, if "Each entry on a separate record" was checked in the Properties Box, Magenta would erroneously give an error if the Segment Length was not greater than or equal to the Data Length.	B			X	4.10
Merge Data	New Merge Data ability to do Segment Preprinting using a Comma/TAB Delimited File.	M			X	4.1
Merge Data	Merging Data is now allowed in Demonstration versions.	M			X	4.10
Merge Data	Added the ability to break on a certain field when using Merge Data and Segments.	M	X	X		4.10
Move cursor	The "Move" cursor had been modified to a more Windows standard cursor.	M	X	X		4.10
Object Bar	Bold and Italic are now separate buttons on the Object Bar for a Response Object to be closer to Windows standard.	M	X	X		4.10
Paper Size	When you adjust the paper size, Magenta now adjusts the number of Timing Marks to fit the new paper size.	M	X			4.10
Properties Dialog Box	Added Dialog Boxes for line, box, shade and graphic objects.	M	X	X		4.10
Properties Dialog Box	Dialog Boxes for lines and boxes have added the ability to create any width line using any line type.	M	X	X		4.10
Properties Dialog Box	Magenta now brings up the Properties Box for each new object created. To turn off this feature, go to Tools/Expert Mode and select.	M	X	X		4.10
Properties Dialog Box	Double clicking on any object will bring the properties box for that object.	M	X	X		4.10
Properties Dialog Box	Added a Properties button to the Object Bar for all object types and a Properties menu item to the File menu to allow easy access to the Object Dialog Boxes.	M		X		4.10
Timing Track	For Magenta Office, removed Timing Track from menu and toolbar.	M		X		4.10

Area	Description	Bug or Mod	Magenta	Concord	Merge Data	Release Version
Wizards	Added New Form wizards for Form parameters, Timing and Skunk Marks.	M	X	X		4.10